

## 0. Deilvery

- What is in the downloaded delivery?




## 1. Software Setup (version: mask-rcnn-resnet50-ver-01.a)

- python 3.6 / Pycharm as IDE
- pytorch 0.4.0 (please build from source. Anaconda/Pip installation is only up to 0.30)



- Software setup. You must build the torch \*.so lib for your system




- 1. lib/box/nms/torch\_nms/extension/\_extension.so
  - >> /usr/local/cuda-9.1/bin/nvcc -c -o nms\_kernel.cu.o nms\_kernel.cu -x cu -Xcompiler -fPIC -arch=sm\_52
  - >> python build

2. lib/roi\_align\_pool\_tf/extension/\_extension.so

This is porting of roi align pooling layer from tensorflow implementation. Note that this is not the same as mask-rcnn paper.

- >> /usr/local/cuda-9.1/bin/nvcc -c -o crop\_and\_resize\_kernel.cu.o crop\_and\_resize\_kernel.cu -x cu -Xcompiler -fPIC -arch=sm\_52
- >> python build

- You must build the cython \*.so lib for your system



- 1. lib/box/nms/cython nms xxx.so
  - >> /opt/anaconda3/bin/python3 setup.py build\_ext
    --inplace
- 2. lib/box/nms/gpu nms xxx.so
  - >> /opt/anaconda3/bin/python3 setup.py build\_ext
    --inplace

To check mns, see "box/process.py" run\_check\_nms()


```
box.py: calling main function ...
gpu_nms : [5, 55, 37, 27, 35, 20, 0, 45, 52, 19, 29, 24, 4, 11]
cython_nms : [5, 55, 37, 27, 35, 20, 0, 45, 52, 19, 29, 24, 4, 11]
torch_nms : [5 55 37 27 35 20 0 45 52 19 29 24 4 11]
sucess!
```


Process finished with exit code 0


- 3. lib/box/overlap/cython\_box\_overlap\_xxx.so
  - >> /opt/anaconda3/bin/python3 setup.py build\_ext
    --inplace

## 2. Data Setup

run the functions at dataset/annotate.py:"run\_make\_train\_annotation()" and "run\_make\_test\_annotation()"







 run the function "run\_check\_dataset\_reader() at dataset/reader.py to see if your data is setu correctly




# 4. Make a submission with the given trained model (00016500\_model.pth)

- This will test if the mask rcnn can run correctly (at inference)
- Run the functions of "submit.py": run\_submit() run\_npy\_to\_sumbit\_csv()

this only make prediction and save results as images and npy.

this read the npy and do post processing to make submission csv

- Example results (see folder "results/mask-rcnn-50-gray500-02/submit")



### 5. Train a model on the dummy images

- Run function "run\_train()" of train\_0.py
- Set both train and validation split to 'disk0\_ids\_dummy\_9'

- This is simple dummy data. You should be able to train all loss to 0! You can see some training visualisation: rpn precision, rcnn precision and mask precision



## 5. Train a model on the gray train images

- Set both train and validation split as follows

```
train_dataset = ScienceDataset(
    'train1_ids_gray2_500', mode='train',
    #'debug1_ids_gray_only_10', mode='train',
    #'disk0_ids_dummy_9', mode='train', #12
    #'train1_ids_purple_only1_101', mode='train',
    transform = train augment)

valid_dataset = ScienceDataset(
    'valid1_ids_gray2_43', mode='train',
    #'debug1_ids_gray_only_10', mode='train',
    #'disk0_ids_dummy_9', mode='train',
    #'train1_ids_purple_only1_101', mode='train',
    #'train1_ids_purple_only1_101', mode='train',
    #'merge1_1', mode='train',
    transform = valid_augment)
```

- this is used to produce model **00016500\_model.pth** 

- An example of training loss is given at: "20180306/results/mask-rcnn-50-gray500-02/log.train.txt"

```
** dataset setting **
                 WIDTH, HEIGHT = 256, 256
                 train dataset.split = train1 ids gray only1 500
                 valid_dataset.split = valid1 ids gray only1 43
                 len(train dataset)
                                       = 500
                 len(valid dataset)
                                       = 43
                 len(train loader)
                                       = 31
                 len(valid loader)
                                       = 3
                 batch size = 16
                 iter accum = 1
                 batch size*iter accum = 16
            ** start training here! **
             optimizer=SGD (
            Parameter Group 0
                 dampening: 0
                 lr: 0.01
                 momentum: 0.9
                 nesterov: False
                                              total loss
                 weight decay: 0.0001
             momentum=0.900000
             LR=None
                                                 rpn loss (classification and regression)
                                                      rcnn loss (classification and regression)
 LK-NOHE
                                                            mask loss
 images_per_epoch = 500
                             valid loss
                                                     | train loss
                                                                               | batch loss
 rate
         iter
               epoch num
                                                                                                           time
                                                0.69 0.00
0.0000
         0.0 k
                             1.994
                                     0.17 0.44
                                                            0.69
                                                                  0.000
                                                                          0.00 0.00
                                                                                                       0.000
                                                                                                                                      0.00
                                                                                     0.00 0.00
                                                                                                 0.00
                                                                                                               0.00 0.00
                                                                                                                          0.00 0.00
                                                                                                                                             0 hr 00 min
                                                                                                                                      0.27
0.0100
         0.1 k
                             0.889
                                     0.06 0.07
                                                0.43
                                                     0.01
                                                            0.33
                                                                 1.020
                                                                          0.08 0.11
                                                                                     0.45 0.04
                                                                                                 0.34
                                                                                                       0.969
                                                                                                               0.08 0.08
                                                                                                                          0.50 0.03
                                                                                                                                             0 hr 04 min
         0.2 k
                             0.857
                                                0.55 0.01
                                                            0.22
                                                                  0.878
                                                                          0.05 0.07
                                                                                     0.47 0.03
                                                                                                       0.836
                                                                                                                                      0.26
                                                                                                                                             0 hr 10 min
0.0100
                 6.4
                     0.0 m
                                     0.04 0.04
                                                                                                 0.25
                                                                                                               0.06 0.07
                                                                                                                          0.42 0.03
0.0100
         0.3 k
                 9.6
                      0.0 m
                             0.717
                                     0.04 0.05
                                                0.41 0.01
                                                            0.22 | 0.832
                                                                          0.05 0.06
                                                                                     0.46 0.03
                                                                                                 0.24
                                                                                                       0.933
                                                                                                               0.02 0.07
                                                                                                                          0.51 0.03
                                                                                                                                      0.30
                                                                                                                                             0 hr 15 min
0.0100
         0.4 k
                12.8
                      0.0 m
                             0.727
                                     0.03 0.04
                                                0.47 0.01
                                                            0.18
                                                                 0.778
                                                                          0.05 0.06
                                                                                     0.43 0.02
                                                                                                 0.22
                                                                                                       0.831
                                                                                                               0.05 0.05
                                                                                                                          0.46 0.03
                                                                                                                                      0.24
                                                                                                                                             0 hr 20 min
        0.5 k
0.0100
                16.0
                     0.0 m
                             0.618
                                     0.03 0.04
                                                0.35 0.01
                                                            0.19 | 0.726
                                                                          0.03 0.05
                                                                                     0.41 0.02
                                                                                                 0.21 | 0.732
                                                                                                               0.00 0.06
                                                                                                                          0.44 0.02
                                                                                                                                      0.21
                                                                                                                                             0 hr 25 min
```

#### 6. Other Evaluation

- Run function "run\_evaluate()" of evaluate.py
- You can measure detection box precision at 0.5, and mask average precision from 0.5 to 1.0
- Results of **00016500\_model.pth** is given at "results-1.xlsx"

SW: mask-rcnn-50-ver-01a				
Results folder: mask-rcnn-50-gray500-02				
train				
train1 ids gray2 500				
	LB metric		test parameters	
	mask avg precision	box precision@0.5	cfg.masl	cfg.rcnn
test				
00016500 model.pth		111111111111111111111111111111111111111		
valid1 ids gray2 43	0.68025	0.86564	0.4	0.3
	0.67847	0.86564	0.6	0.3
train1 ids gray2 500	0.68909	0.89463	0.4	0.3
LB submission (gray53) - 0.419	0.51390	# 0.5139 = 0.419/65	5*53	